Upgrade to ver1.2 from ver1.1 with CE-LK4.

Step1.

Connect cable (CE-LK4) to PC.

Step2.

Execute "CE-LK4 for EL-9950" on PC.

KeyPad FL-0050		
	☐ UNTITLE.GOP Tifie:	

Step3.

Connect cable to EL-9950.

Step4.

Turn on EL-9950 and press $[\pm]$ key. If the following screen is displayed, please press [CL] key twice on EL-9950.

_																
Ρ	R	Е	s	s		[С	L]		Κ	Е	Υ	Т	0	
С	L	Е	Α	R	1	4	L	L		D	Α	т	Α			
Р	R	Е	s	s		[ο	Ν	1		κ	Е	Υ	т	о	
С	Α	Ν	С	ΕI	L											



Step5.

Select "Communication Port" at Link menu.



Step6.

Click "Auto Setting" button.

🙋 SHARP PC-LINK						
File Edit Link Tools	View Window	FuncTable	Help			
Communication Port			×			
				1.G6P	_	
	• A	uto Setting				
OK		Cancel				
MATH STAT PRGM	DEL BS			-		

Step7.

Click "OK" button.



Step8.

The following window is displayed. And a progress bar is extended. When setting is finished, the window is closed automatically.

Auto Setting	8
Port Scanning	Cancel

Note:

If the following window "No response" is displayed, check whether a cable is connect properly. Then do it again from Step6.

SHARP PC	LINK	×
8	No response. Make sure that the cable is correctly connected and that the calculator is turned on.	r
	ОК	

Sep9.

Select "Repro" at Tools menu.



Step10.

Click "Browse" button .

If "el9950_ver120.bin" is already selected, go to Step12.

Repro		
Send File:		
Dillary	1	
	Send	Browse
		Exit

Step11.

Select "el9950_ver120.bin"

Organisieren ▼ Neuer Ordner Favoriten Systemoraner Dektop Systemoraner Downloads Systemoraner Zuletzt besucht Computer Bilder Systemoraner Dokumente Netwerk Musik Systemoraner	🕽 🔵 🗢 📃 Deskto	p ▶	-	• 49	Desktop durchsuc	hen	\$
Favoriten Forwinen Forwinen Forwinen Systemoraner Musik	Organisieren 🔻 🛛	Neuer Ordner				- 🔳	(?)
	Favoriten Desktop Downloads Culetzt besucht Bibliotheken Bibliot Dokumente Musik Nusik		systemoraner shap Systemoraner Computer Systemoraner Netwerk Systemoraner				

Step12.

Click "	Send" butto	n.	
	Repro		—
	Send File: Binary	C:\Users\sharp\Desktop\eU950_ver120.bin	
		Send	Browse
			Exit

Step13.

Click "OK" button.

!	SHARP PC-LINK	
	Make sure that the cable is correctly connected and the calculator is turned on.	
	OK Abbrechen	

Step14.

The following window is displayed.

Repro	
Sending	

After 15seconds, the following screen is displayed on EL-9950.

RE-PROGRAM	RECEIVE
DATA	

Note:

If the following window "No response" is displayed , check whether a cable is connect properly. Please carry out recovery operation(*1) of EL-9950. (Refer to APPENDIX)



If the following window "This is an older version...." is displayed, it is not necessary to upgrade. Because it is already ver1.2.



Step15.

A progress bar is extended.

Repro	
Sending	

A black circle is indicated on EL-9950 during the transfer. After 30 seconds, the first circle is displayed. The total transfer time is about 4 minutes.



Note:

If "x" mark is indicated on EL-9950, Please carry out recovery operation(*1) of EL-9950. (Refer to APPENDIX)



Step16.

When transfer is finished, the following window is displayed. Click "OK" button. EL-9950 is turned off automatically



Step17.

Remove the cable from EL-9950.

Step18.(Last)

Turn on EL-9950. Press [2ndF][OPTION] and [cos] key, then the following screen is displayed. Check name and version. (EL-9950 Ver1.2)



APPENDIX

(*1) Recovery operation of EL-9950

Step A1.

Open and close the battery cover of EL-9950.

Step A2.

If the following screen is displayed, recovery is finished. Please go to Step12.

```
RE-PROGRAM RECEIVE
WAIT
```

If it is not displayed even if it waits for 5 seconds, please turn on EL-9950.

Step A3.

If the following screen is displayed, please press [CL] key twice.

```
PRESS [CL] KEY TO
CLEAR ALL DATA
PRESS [ON] KEY TO
CANCEL
```

Step A4.(Last)

If the screen with only an underline is displayed, recovery is finished. Please go to Step12.

